Arduino institution	Function	Para	Returns			
Dynamixel.begin(Baud_rate, Control_Pin)	Setup Arduino to communicate with Dynamixel servo, this instruction	Baud_rate: this is the speed at who be the same as the Dynamixel	Error code (See table below) 0 = non			
	must be run at lest once	Control_Pin: the output pin on the half duplex buffer chip.				
Dynamixel.end						
Dynamixel.reset(Servo_ID)	Reset the Dynamixel servo back to factory default	Servo_ID: Servo ID of which the	Error code (See table below) $0 = \text{non}$			
Dynamixel.ping(Servo_ID)	Ping the Dynamixel servo and receive status packet from Dynamixel servo	Servo_ID: Servo ID of which the	Returns = Servo ID of Pinged servo Error code (See table below)			
Dynamixel.setStatusPaketReturnDelay(Servo_ID, Return_Delay)	The delay between Dynamixel servo	Servo_ID: Servo ID of which the	institution will be addressed too	Returns = Servo ID if		
	receiving an instruction packet from the Arduino and the Dynamixel servo returning(sending) status packet.		Return_Delay: Return delay value (in uSec) Dynamxiel Default Value = 500 uSec)			
Dynamixel.setBaudRate(Servo_ID, Baud_Rate)	Set a new baud rate speed on the	Servo_ID: Servo ID of which the	Returns = Servo ID if setStatusPacket is set to ALL			
	Dynamixel servo	Baud_Rate: New Baud rate to wh				
		Target BPS	Error Between Dynamixel and Arduino	Error code (See table below)		
		3000000	0.000 %			
		2500000	0.000 %			
		2250000	0.000 %			
		1000000	0.000 %			
		500000	0.000 %			
		400000	0.000 %			
		250000	0.000 %			
		200000	0.000 %			
		115200	-2.124 %			
		57600 (Dynamixel Default)	0.794 %			
		19200	-0.160 %			
		9600	-0.160 %			
Dynamixel.setMaxTorque(Servo_ID, Torque)	Set max torque value which when	Servo_ID: Servo ID of which the	Returns = Servo ID if setStatusPacket is set to ALL Error code (See table below) Returns = Servo ID if setStatusPacket is set to ALL Error code (See table below)			
	reached the Dynamixel will alarm and shut down	Torque: value of max torque (value) (Dynamxiel Default Value = 0x3)				
Dynamixel.setHoldingTorque(Servo_ID, Bool)	Set holding torque	Servo_ID: Servo ID of which the				
y	0.0140	Bool: ON = Holding torque true,				

		OFF = Holding torque false					
Oynamixel.setAlarmShutdown(Servo_ID, Alarms)	_	Servo_ID: Servo ID of which the institution will be addressed too	Returns = Servo ID if setStatusPacket is set to ALL				
	monitor	Alarms: which alarm bits will be set (see Robotis manual for bit					
		define)	Error code (See table below)				
Dynamixel.setStatusPaket(Servo_ID, Status)	Set when the Dynamixel will or will	Servo ID: Servo ID of which the institution will be addressed too	Returns = Servo ID if				
·	not return a status packet	Status:	setStatusPacket is set to ALL				
		NONE = no status packet are returned from Dynamixel. READ = only read instructions return a status packet. ALL = all instructions return a status packet	Error code (See table below)				
Oynamixel.setMode(Servo_ID,bool,CW_Limit,CCW_Limit)	Set servo to "wheel" mode or "servo"	Servo_ID: Servo ID of which the institution will be addressed too	Returns = Servo ID if setStatusPacket is set to ALL				
	mode and set angel limits for servo	Bool:					
	mode	WHEEL = wheel mode. SERVO = servo mode.	Error code (See table below)				
		CW_Limit: angel limit for clockwise movement (value range 0x01 to					
		0xFFF) one unit is about 0.088 degrees					
		e.g 0xFFF x 0.088 is about 360 degrees					
		CCW_Limit: angel limit for anticlockwise movement (value range					
		0x01 to 0xFFF)					
		one unit is about 0.088 degrees e.g 0xFFF x 0.088 is about 360 degrees					
Oynamixel.setPunch(Servo_ID, Punch)	Set Punch value	Servo_ID: Servo ID of which the institution will be addressed	Returns = Servo ID if				
_ /		tooReturns = Servo ID if setStatusPacket is set to ALL	setStatusPacket is set to ALL				
		Error code (See table below)	Error code (See table below)				
		Punch: Punch value					
Oynamixel.setPID(Servo_ID, P_Gain, I_Gain, D_Gain)	Set PID settings	Servo_ID: Servo ID of which the institution will be addressed too	Returns = Servo ID if setStatusPacket is set to ALL Error code (See table below)				
Oynamixel.setPunch(Servo_ID, Punch) Oynamixel.setPID(Servo_ID, P_Gain, I_Gain, D_Gain) Oynamixel.set.Temp(Servo_ID,Temp) Oynamixel.setVoltage(Servo_ID, Lowest_Volt, Highest_Volt)		P_Gain: Proportional ban					
		I_Gain: Integral action					
		D_Gain: Derivative action					
Oynamixel.set.Temp(Servo_ID,Temp)	Set highest temperature alarm limit	Servo_ID: Servo ID of which the institution will be addressed too	Returns = Servo ID if				
		Temp: Temperature value in Celsius	setStatusPacket is set to ALL				
			Error code (See table below)				
Oynamixel.setVoltage(Servo_ID, Lowest_Volt, Highest_Volt)	Set lowest and highest voltage alarm	Servo_ID: Servo ID of which the institution will be addressed too	Returns = Servo ID if				
	limits	Lowest_Volt: Low voltage limit	setStatusPacket is set to ALL				
		Highest_Volt: High voltage limit	Error code (See table below)				
Oynamixel.servo(Servo_ID, Angle, Speed)	Move in servo mode to a specific	Servo_ID: Servo ID of which the institution will be addressed too	Returns = Servo ID if setStatusPacket is set to ALL				
	angle at speed "x"	Angle: Angle to move servo too (value range 0x00 to 0xFFF)					
		one unit is about 0.088 degrees	Error code (See table below)				
		e.g 0xFFF x 0.088 is about 360 degrees					
		Speed: Speed to move at (value range 0x00 to 0x3FF) one unit is about 0.114rpm					

		e.g 0x3FF x 0.114 is about 117.07rpm		
Dynamixel.servoPreload(Servo ID, Angle, Speed)	Write to Dynamixel register the servo	Servo ID: Servo ID of which the institution will be addressed too	Returns = Servo ID if setStatusPacket is set to ALL Error code (See table below)	
	mode to a specific angle at speed "x" NOTE: this conman only writes(stores) the instruction on the	Angle: Angle to move servo too (value range 0x00 to 0xFFF) one unit is about 0.088 degrees e.g 0xFFF x 0.088 is about 360 degrees		
	Dynamixel, you must then use "Dynamixel.action" to tell it to action the information in the Dynamixel register.	Speed: Speed to move at (value range 0x00 to 0x3FF) one unit is about 0.114rpm e.g 0x3FF x 0.114 is about 117.07rpm		
Dynamixel.wheel(Servo_ID, Direction, Speed)	Move in wheel mode left/right at	Servo_ID: Servo ID of which the institution will be addressed too	Returns = Servo ID if	
	speed "x"	<i>Direction:</i> _RIGHT = clockwise, LEFT = Anti-clockwise	setStatusPacket is set to ALL	
		Speed: Speed to move at (value range 0x00 to 0x3FF) one unit is about 0.114rpm e.g 0x3FF x 0.114 is about 117.07rpm	Error code (See table below)	
Dynamixel.wheelPreload(Servo_ID, Direction, Speed)	Move in wheel mode left/right at	Servo_ID: Servo ID of which the institution will be addressed too	Returns = Servo ID if	
	speed "x"	<i>Direction:</i> _RIGHT = clockwise, LEFT = Anti-clockwise	setStatusPacket is set to ALL	
		Speed: Speed to move at (value range 0x00 to 0x3FF) one unit is about 0.114rpm e.g 0x3FF x 0.114 is about 117.07rpm	Error code (See table below)	
Dynamixel.action(Servo_ID)	Tell Dynamixel to action any instruction stored in its register	Servo_ID: Servo ID of which the institution will be addressed too	Returns = Servo ID if setStatusPacket is set to ALL	
			Error code (See table below)	
Dynamixel.readTemperature(Servo_ID)	Get Dynamixel Temperature in C	Servo_ID: Servo ID of which the institution will be addressed too	Error code (See table below) & Temperature in Celsius	
Dynamixel.readVoltage(Servo_ID)	Get Dynamixel Voltage	Servo_ID: Servo ID of which the institution will be addressed too	The HEX value returned is ten time the real value.	
			e.g return value of 109 is 10.9 Volts	
			Error code (See table below) & Voltage	
Dynamixel.readPosition(Servo_ID)	Get Dynamixel Position (angle)	Servo_ID: Servo ID of which the institution will be addressed too	one unit is about 0.088 degrees e.g 0xFFF x 0.088 is about 360 degrees	
			Error code (See table below) & Posistion	
Dynamixel.readLoad(Servo_ID)	Get Dynamixel load and direction of load force on the Dynamixel	Servo_ID: Servo ID of which the institution will be addressed too	Error code (See table below) & Load	
Dynamixel.readSpeed(Servo_ID)	Get speed at which the servo is turning	Servo_ID: Servo ID of which the institution will be addressed too	one unit is about 0.114rpm e.g 0x3FF x 0.114 is about 117.07rpm	
			Error code (See table below) & Speed	

Dynamixel.checkRegister(Servo_ID)	Check if there are any commands in register e.g Dynamixel.servoPreLoad()	Servo_ID: Servo ID of which the institution will be addressed too	Error code (See table below) & 0 = Non 1 = Yes	
Dynamixel.checkMovement(Servo_ID)	Check to see if servo is still moving to goal angle	Servo_ID: Servo ID of which the institution will be addressed too	Error code (See table below) & 0 = Goal angle complete 1 = Goal angle still in progress	
Dynamixel.checkLock(Servo_ID)	Check to see if the Dynamixel has EEPROM locked	Servo_ID: Servo ID of which the institution will be addressed too	Error code (See table below) & 0 = EEPROM can be modified 1 = EEPROM can not be modified	
Dynamixel.ledState(Servo_ID, State)	Turn LED on Dynamixel off/on	Servo_ID: Servo ID of which the institution will be addressed too	Error code (See table below) $0 = \text{non}$	
		State: ON = turn LED on OFF = Turn LED off		

	ERROR CODES														
Bits															
15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
	Bit(s) are 1 when there is and error, Bit(s) are 0 when there is no error														
Bit 0	Dynamixel in	Dynamixel input voltage error (Voltage out side of set range)													
Bit 1	Dynamixel a	Dynamixel angle limit error (Goal position is outside angle limits)													
Bit 2	Dynamixel o	Dynamixel over heating error (Temperature is above set limit)													
Bit 3	Dynamixel o	Dynamixel command is beyond range of use													
Bit 4	Dynamixel C	Dynamixel Checksum error (packet received has invalid checksum)													
Bit 5	Dynamixel C	Dynamixel Overlaod error (current load can not be controlled with the present maximum torque)													
Bit 6	Dynamixel I	nstruction erro	or (A undefine	d instruction ha	as been send o	r action comn	nand is invalid)								
Bit 7	Recived statu	ıs packet error	r (there has no	ot been any stat	us packet rece	eived by Ardu	ino)								
Bit 8	None	None													
Bit 9	None	None													
Bit 10	None	None													
Bit 11	None	None													
Bit 12															
Bit 13	All 4 are set	1 when there	is a error on a	ny of the above	e, 0 if there is	no error									
Bit 14						ır bits are set ((0xF000) so if t	hese bits are	set there is ar	n error and oth	er bits can be	check as per th	is table to find	l out error. If bi	t 12 to 15
Bit 15	are zero all o	ther data retur	As the Dynamixel does not use the bit 12 to 15 for any data, these four bits are set (0xF000) so if these bits are set there is an error and other bits can be check as per this table to find out error. If bit 12 to 15 are zero all other data returned is valid e.g. temp, volt e.t.c.												







